Genetic mapping and manipulation: Chapter 4-SNPs: Introduction and two-point mapping*

David Fay[§], Aaron Bender, Department of Molecular Biology, University of Wyoming, Laramie, Wyoming 82071-3944 USA

Table of Contents

1. Basics	1
2. The SNP database	2
3. Using different types of SNPs	
4. Two-point mapping with SNPs	
5. Worm PCR protocol	
5.1. Reagents	
5.2. SNP mapping PCR	
6. References	

1. Basics

Mapping with SNPs has become a powerful complement (and in some cases outright alternative) to the standard genetic mapping procedures described above. In fact, the advent of SNP mapping has been nearly as significant for *C. elegans* forward genetics as RNAi has been for reverse genetics. With SNP mapping, basically all mutations are now theoretically clonable, something that wasn't true in the past. Moreover, SNP mapping can be routinely used to narrow down the known physical location of mutations to regions smaller than a single cosmid (~30,000 bp; ~6-7 genes). With genetic mapping, even in the best of circumstances, the implicated regions usually span 6-10 complete cosmids or more. In fact, SNP mapping can theoretically be used to narrow down the implicated region to a single gene, although this level of mapping is usually unnecessary and can become inordinately time consuming.

Although several approaches for mapping using polymorphisms have been described, we will focus here on the use the Hawaiian *C. elegans* isolate, CB4856 (Jakubowski and Kornfeld, 1999; Koch et al., 2000; Wicks et al., 2001; Swan et al., 2002). Because of geographical separation, several million years of evolutionary drift have led to a sizeable number of genetic differences (DNA polymorphisms) between the Hawaiian and English (N2) *C. elegans*

^{*}Edited by Victor Ambros. Last revised May 4, 2005. Published February 17, 2006. This chapter should be cited as: Fay, D. and Bender, A. Genetic mapping and manipulation: Chapter 4-SNPs: Introduction and two-point mapping (February 17, 2006), *WormBook*, ed. The *C. elegans* Research Community, WormBook, doi/10.1895/wormbook.1.93.1, http://www.wormbook.org.

Copyright: © 2006 David Fay and Aaron Bender. This is an open-access article distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited.

[§]To whom correspondence should be addressed. E-mail: davidfay@uwyo.edu

populations. In fact, differences in the genomic sequences of CB4856 and N2 occur on average every 1,000 base pairs. The majority of these changes occur in non-coding or intergenic regions and probably have no functional consequence. Some polymorphisms, however, clearly affect protein activity or gene expression, as N2 and CB4856 differ notably in a number of respects including their mating behaviors and relative sensitivities to RNAi (also see below).

The term SNP is a bit of a misnomer. Although many of the sequence variations between N2 and CB4856 are indeed single-nucleotide changes (for example from an A to a G), small deletions or insertions are also very common. What is experimentally most relevant, however, is whether or not these polymorphisms affect the recognition site for an endonuclease. SNPs that result in restriction-fragment length polymorphisms (RFLPs; also called snip SNPs) are easier to work with, as digestion by enzymes is much more rapid and inexpensive then sending off samples for sequencing. Also, it generally doesn't matter whether it's the N2 or CB4856 DNA that is cleavable (however, also see below), just so long as the digestion patterns of the two isolates are clearly distinguishable.

2. The SNP database

The *C. elegans* SNP database contains only a *partial listing* of the many polymorphisms that undoubtedly exist between N2 and CB4856. Nevertheless, this resource provides a very useful (if incomplete) inventory of SNPs for the strains N2 and CB4856. The SNP database is organized according to the physical map by chromosomes, chromosomal subsegments, and cosmids. For example, at the top of sequence Segment 9 on Chromosome X, you will find the SNP B0403:33022 S=CT. This means the polymorphism is on cosmid B0403 at nucleotide position 33,022 and that the two strains differ in having either a C or T at this position. SNPs listed in red lettering have presumably been experimentally confirmed, whereas SNPs listed in white lettering are as yet unconfirmed. In fact, our lab has had at least one bad experience with a "confirmed" SNP, *thus it is essential to make sure that any SNP you work with behaves as expected in your own hands*.

Clicking on the red letters of B0403:33022, we bring up an additional window that shows the actual sequences surrounding the SNP in black lettering (usually ~500 bp upstream and downstream) as well as the SNP itself in red lettering [C/T]. This designation indicates that N2 contains a C at this position whereas CB4856 contains a T. Also, if it is an RFLP-type SNP, the top of this page will show predicted digestion sites for the displayed DNA sequence from N2 and CB4856 (listed here as "HA" for Hawaiian), using one or more enzymes. Looking at this, we notice that in the CB4856 background the presence of the T results in the sequence AGATCT, which is the recognition site for the restriction enzyme *BglII*. This enzyme cuts once in this segment of the CB4856 sequence and not at all in N2. Thus if we were to amplify this region from N2 and CB4856 worms using PCR and cut the PCR product with BglII, CB4856 would produce a doublet of about 500 bp each, whereas N2 would run as a single band of 1,000 bp. The other enzymes listed as distinguishing this polymorphism (e.g., *MnII* and *MboI*) although technically correct, are not of much practical use, as they cut many times in both N2 and CB4856 sequences. Therefore, discerning these two largely identical digestion patterns (using a standard agarose gel) would be difficult or impossible.

Moving down to the unconfirmed SNP just below B0403, we find C36B7:21571. The presence of a C in N2, and an A in CB4856, leads to the creation of a new site for the enzyme *Apol* (consensus RAATTY; where R is an A or G and Y is a C or T. For a complete listing of abbreviations, see the back of the NEB catalog). Here we see that Apol cuts five times in strain CB4856 (59, 405, 500, 638, 648). Directly above this, we see that the N2 digest is listed as "none". *Beware: this does not mean that CB4856 cuts five times with Apol and not at all in N2!* In fact, N2 cuts four times with Apol (59, 405, 638, 648), just not at the middle position where the actual SNP is located (500). This is obviously misleading. By "none", they just mean that the polymorphism results in no new enzyme sites that specifically cut the N2 sequence. Another thing to be aware of is that for non-palindromic sites, it may be the bottom (non-scripted) strand of DNA that is relevant.

Because many of the listed SNPs are not experimentally confirmed, the question arises: how many SNPs are actually real and is it possible to intuitively distinguish the real ones from the false ones? (The false ones are simply due to errors in the single sequencing reads of CB4856). For all non-confirmed SNPs, a probability index (Psnp) is given at the top of the page that contains the sequence information. For C36B7:21571, the Psnp is 0.9427, meaning that there is supposedly a 94% chance that the SNP is real based on the quality of the read. For a non-confirmed SNP, this is as good as it gets. Also, if you've ever stared at the electropherogram from a sequencing read, you'd know that it would be difficult under most circumstances (even for a computer) to mistake a C for an A. In contrast, it is our experience that SNPs with Psnp indices below 0.5 are invariably bogus. In addition, SNPs that result in single base-pair deletions or insertions within a run of repetitive nucleotides (e.g., A7 versus A8) are often suspect.

Although some of these may turn out to be real, common sense dictates that sequencing errors are more likely to occur when attempting to distinguish between these sorts of differences than when comparing sequences such as ATG and ACG. Thus, you will want to use some discretion in your true/false predictions beyond the Psnp index. Of course, you will always want to substantiate or disprove any unconfirmed SNP before attempting any significant mapping exercises, no matter what the probability index or your intuition tells you.

As described below, most fine mapping will require that the investigator identify new SNPs that are not currently in the database. This is simply done by amplifying random intergenic sequences in the region of interest from CB4856. We usually amplify an ~1,600-bp region and use two internal sequencing primers that point inward. The sequences obtained can then be used in BLAST searchers against the N2 sequence to identify polymorphisms. Potential differences are always further confirmed by looking at the electropherogram readouts. More often than not, one will find at least a single difference within a region of this size.

3. Using different types of SNPs

An assessment of any SNP requires that the chromosomal region containing the polymorphism be amplified directly from worms (see below SNP PCR procedure). For SNPs that have been confirmed, the suggested primer sequences for amplification are indicated at the top of the window that contains the DNA sequence as well as by lower-case letters within the sequence text itself. These may often be a wise choice, although you will want to ultimately pick your primer sites based on two criteria: 1) the sites should enable you to make a clear distinction between N2 and CB4856 sequences, and 2) the primers should not anneal to other sites within the *C. elegans* genome. For the former concern, keep in mind that it is easier to distinguish the difference between one 800- and two 400-bp bands than one 400- and two 200-bp bands. This is because the smaller the bands get, the harder it may be to resolve subtle differences, and also the more likely that these bands will be partially obscured by the fuzzy primer band that runs near the bottom of every gel. Thus although it might be marginally easier to amplify the 400-bp band, the clouded interpretation will negate any positive benefits. In addition, it is extremely prudent to carry out a BLAST search on any primer that you intend to use prior to ordering. In the case that you uncover many perfect or near-perfect matches to the primer elsewhere in the genome (particularly to the 3'-most 15 or so nucleotides), go back to the drawing board and find another sequence that won't be as likely to give you high backgrounds.

Non-RFLP SNPs, although obviously harder to use than RFLP SNPs, can nevertheless be invaluable tools. This is particularly true once one has significantly narrowed down the genetic region containing the mutation of interest. At this point, you will have probably whittled down your informative recombinants to a workable number. Thus, any sequencing efforts will be less arduous and less expensive. Note that when testing non-RFLP SNPs by sequencing, always use an internal sequencing primer (not one of the outer primers used for amplifying the DNA), and place the 3' end of the primer at least 50 base pairs away from the SNP site to avoid messy or ambiguous reads. In addition to sequencing, we have recently begun testing the use of the Surveyor mutation detection kit from Transgenomic (tip of the hat to E. Hague). The detection method exploits the production of a small bubble of single-stranded DNA in re-annealed hybrids of N2 and CB4856 DNAs that contain sequence variations. A nuclease that recognizes the DNA distortion then cleaves both strands, which can be detected on a gel. Although this method is not nearly as straightforward as a restriction enzyme digest, it may avoid the time and expense of sending out PCR products for sequencing and could ultimately make non-RFLP SNPs more attractive to use. However, the general utility of this method is (at least in our hands) currently unclear.

4. Two-point mapping with SNPs

For all standard SNP mapping, you will want to generate and maintain a stock of CB4856 males. The males are then crossed into your mutant strain to generate heterozygous cross progeny that are allowed to self, leading to the regeneration of your homozygous mutant. In certain situations (such as for mapping suppressors and enhancers), you may want to generate versions of your mutant strains that have been extensively outcrossed to CB4856, and then use males from these stocks instead of from CB4856 (also see below). Figure 1 shows the basic scheme for two-point SNP mapping. Just as in two-point genetic mapping, the closer your mutation lies to the given SNP being tested, the less likely that a homozygous mutant will harbor a CB4856 allele of that polymorphism, and the more likely that there will be a significant over-representation of N2 homozygous loci among mutant animals.




Figure 1.

In the event that your mutation lies on the far arm of a chromosome, linkage can still be reliably detected using a central SNP. For example, if the mutation and SNP are separated by 25 map units, ~56% of homozygous mutant animals should be homozygous N2 for the SNP (38% will be N2/CB and 6% CB/CB). In the case that your mutation is unlinked from the SNP being tested, homozygous mutants will segregate N2/N2: N2/CB: CB/CB animals in the standard 1:2:1 ratio. Thus 75% of the homozygous mutant animals will be either N2/CB (50%) or CB/CB (25%), whereas only 25% will be N2/N2. For additional details on calculating predicted percentages based on genetic distance, see (Two-point mapping with genetic markers).

One helpful tactic is to use CB4856-specific cutters as SNPs whenever possible. The reason for this has to do with making the interpretation of data from animals that are a mixture of N2 and CB4856 (50% in the case of non-linkage) as unambiguous as possible. Namely, if you were to use an N2-specific cutter and observed a small amount of residual uncut PCR product on your gel (as well as bands indicating cleavage), you might conclude that the uncut DNA demonstrates the presence of some CB4856 DNA for that locus in the strain. Thus, the re-isolated mutant strain would be scored as a mixture of N2 and CB4856. However, cleavage by restriction enzymes is seldom complete, and you wouldn't know whether the residual uncut band was due to an incomplete digest or the presence of non-cleavable (CB4856) DNA. Contrast this with using a CB4856-specific cutter: in this situation, the appearance of even a small amount of cut DNA of the correct size would strongly support the presence of some CB4856 DNA at that locus. Of course, it is also true that homozygous CB4856 DNA may not cut to completion either. However, the distinction between N2/CB and CB/CB classes of strains is far less critical than recognizing strains that are truly homozygous for N2. Thus, the assignment of N2 homozygous and N2-non-homozygous isolates is much cleaner when using CB4856-specific cutters.

There are several other considerations in carrying out two-point SNP mapping. First, because we only pick a limited number of animals for any given PCR reaction, the possibility of randomly picking several animals that are homozygous for a given SNP from a mixed plate increases as we pick fewer animals. For this reason, it is always advisable to pick at least five adults for each tube, or to pick piles of larvae from starved plates. Also, when propagating the strains, make sure either to chunk the plates (by transferring a piece of the agar) or to transfer large numbers of animals by pick to preserve the heterogeneous status of the mixed plates. In addition, *it is critical to limit the number of generations that the strains have undergone prior to SNP testing.* Part of the rationale for this is described above. Moreover, it has been our experience (and that of others) that mixed populations may drift towards homozygosity of specific N2 or CB4856 alleles or chromosomes not simply via a random process but through active

selection. For example, we have observed a strong selection in N2/CB strains to homozygose the N2 X chromosome. Thus it is essential to obtain the required SNP data from your collection of mutant isolates rapidly to avoid the biasing that may take place after multiple generations. Also, it is a better idea to let your plates starve out while you're doing the testing than to continually passage them to new plates, thus minimizing any selection that may (want to) take place.

Once you have assigned a linkage group to your mutation based on two-point SNP mapping data, it may be possible to refine the position of the mutation by testing other regional SNPs. For example, if you had assigned your mutation to a specific chromosome based on the observation that 35/40 of the mutant isolates were homozygous for the N2 locus, it may be possible to test new SNPs that are several map units to either side. Thus you may find a new locus where 39/40 mutants contain the homozygous N2 allele, indicating a closer linkage to your mutation. You will also want to choose a good pair of genetic markers for quickly confirming your SNP result by standard two-point mapping. This will not only serve the purpose of independently confirming your SNP results but will also allow you to begin the process of genetic three-point mapping (Three-point mapping with genetic markers).

5. Worm PCR protocol

5.1. Reagents

10% PCR Buffer

100 mM Tris-HCl (pH 8.8) 500 mM KCl 0.8% NonIdet p40 detergent

Lysis Buffer

50mM KCl 10 mM Tris-HCl (pH 8.3) 2.5 mM MgCl₂ 0.45% Nonidet P-40 0.45% Tween 20 0.01% (w/v) gelatin (Autoclave and store aliquots at -20°C)

Proteinase K (10.0 mg/ml)

MgCl₂ (25mM)

dNTP's (2.5 mM each)

DNA polymerase (5 units/Rxn)

PCR primers (10.0 pmol/μl)

5.2. SNP mapping PCR

Add 1 μ L of 10.0 mg/mL proteinase-K to 99 μ L of lysis buffer and mix well. It may be necessary to scale up depending on the number of PCR reactions to be done. Add 3.0 μ L of mix to the open lids of several 0.2 ml PCR tubes. Pick 1 to 5 worms and place them in the drop of solution in the tube lid by swirling pick within the liquid. Be sure that all the worms are in the lid before proceeding. Next, close the lid of the tube and spin in a microfuge for 10 seconds. You can transfer worms to multiple tubes prior to spinning, provided the samples are not left at room temperature for too long. After centrifugation, place the tubes on ice in a 96-hole PCR tube rack. When finished, place the rack at -70°C for 45 minutes (or longer). Next, place the tubes in a thermocycler and run the following sequence: 65°C 1 hr, 95°C for 30 min., 4.0°C hold. The proteinase-K is active at 65°C but is efficiently de-activated at 95°C. The heat-deactivation is crucial because the proteinase can cleave the polymerase during PCR.

After the lysis reaction is completed, the lysate can be used directly for PCR or stored at -70°C. Prepare a master mix containing the following ratios of ingredients:

Genetic mapping and manipulation: Chapter 4-SNPs: Introduction and two-point mapping

13.5 µL dH20
2.5 µL 10x PCR buffer
1.5 µL 25.0 mM MgCl
2.25 µL forward primer
1.25 µL reverse primer
1.0 µL dNTP's (2.5 mM each)
1.0 µL Taq DNA polymerase (~ 5U)

After the lysis reaction is completed, the lysate can be used directly for PCR or stored at -70°C. Prepare a master mix containing the following ratios of ingredients:

Mix the solution well and add $22.0~\mu L$ to each tube containing $3.0~\mu L$ of worm lysate. Be aware that the ingredients for the PCR master mix can vary depending on the polymerase used. Read the manufacturer's recommendations carefully. Most manufacturers provide 10x buffer and a tube of MgCl or MgSO₄ with the polymerase. Also, when putting together the master-mix, don't forget to make a bit extra for the PCR fairies. For example, if you are carrying out 20 reactions, make enough mix for 22.

It is often difficult to guess at ideal thermocycling conditions for PCR (principally the annealing temperature). Therefore, it is best to determine these conditions prior to conducting PCR for mapping purposes. If you have access to a thermocycler that is capable of running temperature gradients, ideal conditions can be determined in a single step. Set the annealing temperature for the center rows of the machine at the Tm given on the lyophilized primer tubes provided by the manufacturer. Next, program the machine to run a 10°C temperature gradient. This often means that during the annealing step, the leftmost column will be 10°C cooler than the center columns and the rightmost column 10°C warmer. This effectively results in a 20°C difference between the left and right columns. Most gradient thermocyclers allow you to view the exact annealing temperature in each column for a given reaction. Record these so you can keep track of the ideal annealing temp for future reactions. Prepare 12 reactions for N2 and 12 for CB4856. Place them in parallel rows within the machine (i.e. A1 - A12: N2 and B1 - B12: CB4856). For the initial PCR reaction, set the following conditions:

- 1. 95°C 2.0 min. (initial denaturation)
- 2. 95°C 45 sec. (denaturation)
- 3. Annealing step 30 sec. (see above)
- 4. 72°C 2.0 min/kB (extension)
- 5. Repeat steps 2, 3, and 4, 30 to 40X
- 6. 4.0°C hold

After the reaction is finished, run a 0.8-1.2% agarose gel and stain with EtBr. The ideal annealing temp will correspond to the lane/lanes on the gel where a single strong PCR product of the correct size is seen. This is usually the same temp for N2 and for CB4856. Aberrant bands can often be attributed to non-specific annealing of the primers to other genomic fragments. This can usually be corrected by using a higher annealing temperature. The gradient reaction is valuable for empirical determination of annealing temperature in one step. However, if a gradient machine is not available, set the initial annealing temp at or somewhat above (5-10°C) the Tm on the primer tubes.

Once the ideal annealing temp is found, digest both the N2 and CB4856 samples with the appropriate restriction enzyme to be sure that the difference in fragment sizes correspond to the SNP database predictions and can be readily determined. Usually we digest \sim 5 μ l of the PCR reaction in a total volume of 10 μ l for several hours. It is often useful to run the un-digested PCR product next to digested product for each recombinant. This is particularly helpful when primer sets or conditions produce non-specific amplimers that might be confused with digest products. Also, don't forget to always include N2 and CB4856 control reactions when doing SNP mapping experiments. For this purpose, we usually have one hand genomic DNA from large-scale preps of these two strains.

We would also mention that primer design is of the utmost importance in getting SNPs to work. A number of free WEB-based programs are available that will aid in minimizing secondary structure and optimizing and matching melting temperatures. We also find it useful to conduct BLAST searchers of the proposed primers to avoid those that may be complementary to multiple locations within the genome. In some instances, bad primer sets cannot be predicted. In these cases we simply order two more primers and then perform a mix and match experiment with the old and new primers to determine the pair that works the best. We also prefer, when possible, to use primers

that amplify fragments of 750-1,000 bp. This is somewhat larger than many of the suggested primers sites often described on the SNP database (~500 bp). In our experience, slightly larger fragments are somewhat easier to interpret, since the cut products still run well above the junk (primer-dimer bands) at the bottom of the gel. However, in some cases, this advantage isn't necessary or may be offset by the decreased efficiency of amplifying a larger band.

6. References

Jakubowski, J., and Kornfeld, K. (1999). A local, high-density, single-nucleotide polymorphism map used to clone Caenorhabditis elegans cdf-1. Genetics 2, 743–752. Abstract

Koch, R., van Luenen, H.G., van der Horst, M., Thijssen, K.L., and Plasterk, R.H. (2000). Single nucleotide polymorphisms in wild isolates of Caenorhabditis elegans. Genome Res. 11, 1690-1696. Abstract Article

Swan, K.A., Curtis, D.E., McKusick, K.B., Voinov, A.V., Mapa, F.A., and Cancilla, M.R. (2002). High-throughput gene mapping in Caenorhabditis elegans. Genome Res. 7, 1100-1105. Abstract Article

Wicks, S.R., Yeh, R.T., Gish, W.R., Waterston, R.H., and Plasterk, R.H. (2001). Rapid gene mapping in Caenorhabditis elegans using a high density polymorphism map. Nat. Genet. 2, 160-164. Abstract Article

